

© 2015 Laura Denison. All rights reserved. Purchase of this pattern allows you to make one or more albums for non-commercial use. Unless granted in writing by the designer/author in advance, copying, faxing, or reproducing the pattern, instructions or designs in any manner, digitally or otherwise is strictly prohibited by United States copyright law.


© 2015 Laura Denison


This album features pocket pages with added flaps and pockets. You may select the flaps and pockets you wish to use on each page. This album can be styled and embellished to fit any theme. This album features the On the Hook Binding system.

The supplies listed below are to make the project. Additional papers and embellishments can be added to make your project uniquely your own.

Materials list

- Patterned paper (12 x 12, 8 x 8 and/or 6 x 6)
- -(12) 8 1/2" x 11" cardstock for page bases
- (8 ea) of 4 different $8 \frac{1}{2}$ " x 11" cardstock for page flaps and pockets.
- (2) $7 \frac{1}{2}$ x 8 $\frac{1}{2}$ rectangles of mid-weight chipboard (.050) for covers
- -(1) 4" x 8 1/2" rectangle of lt weight (.022) for spine
- Fabric to cover spines (6" x 22")
- Embellishments (Envelopes, tags, punches, die-cuts, flowers, stickers, etc. as desired)





Create pocket page bases by cutting a 8" x 8 1/2" and a 7 1/4" x 8 1/2" rectangle from page base cardstock. Score larger at 1/2" along top edge and at 1/2" and 3/4" from one edge. Score smaller sheet at 1/2" at top edge.

Trim corner at intersection on larger sheet. Create a sleeve pocket page base by attach 1/2" tabs on top and bottom edge. Fold tabs away from pocket. Make six pages.

© 2015 Laura Denison



On the Hook Binding


Pages are attached together with hooked tabs. The tabs will attach to the sleeve of the proceeding page.




Attach 1/2" tab section into the sleeve of the previous page with glue or strong adhesive.

Alignment of the folds of the 1/4" spine channels will yield a cleaner spine.

© 2015 Laura Denison



For the attach ment of the cover to the back page, cut a 1 1/4" x 8" strip. Score at 1/2" from edges to create a channel.



Attach one fin of the channel into the sleeve of the last album page.

© 2015 Laura Denison






For inside spine, cut a 3" x 8 1/2" piece of fabric or patterned paper.

Turn under top and bottom edge 1/4". Use adhesive or lue to fold over edge.



Apply strong adhesive to spine channels as shown.



Cover inner spine with fabric or patterned paper.

© 2015 Laura Denison



Aligned folded over edge of fabric with the edge of the cardstock pages.




Attach covers with glue or strong adhesive, centered.

© 2015 Laura Denison



Wrap fabric to outside of album.



Cover the cover with patterned paper, splicing as needed.

© 2015 Laura Denison



Score lightweight chipboard at 1/2" from each side. Score at 1/4" and 2" from each side.

Turn under eges along 1/2" tab. Attach.



Cover out spine with fabric, wrapping 1/2" on all edges.

Attach spine to cover by attaching folded edge section onto edge of cover maintaining the joint at 1/4" from edge of cover.

© 2015 Laura Denison





Attach remaining side to back cover.

Pick any of the following page styles and apply to page face.

© 2015 Laura Denison





Z fold Flap Page

Score and fold an 8 1/2" x 11 sheet of cardstock at 4" from one edge and at 1/2" along opposite edge.

Fold flap over on front of page.

Cut a 3 1/2" x 8 1/2" strip of cardstock. Score 1/2" tabs on 3 sides of panel.

Cut a 2" band from cardstock for inside belly band.

Attach flap to edge of pocket/page.

Attach pocket to face of flap and belly band on inside of flap.



© 2015 Laura Denison

Pocket Flap Page

Cut a 5 1/2" x 7 3/4" pocket base Cut a 5 1/2" x 8 1/2" pocket

Score a fold pocket base at 1/2" along one long edge.

Score and fold 3/8" tabs along sides and a 1/2" tab along bottom.

Attach pocket to pocket base, allowing pocket to extend 1/2" above top edge of pocket base.

Attach pocket base to page, centered and 1/8" from edge of pocket.







© 2015 Laura Denison



Double Flap Page


Cut a 7 3/4" x 8 1/2"

Score and fold at 5" and 5 1/2"

Attach to page base at channel



© 2015 Laura Denison



Gatefold Flap Page

Cut (2) 5 1/2" x 8" flaps

Score and fold a 1/2" tab along one side and a 1/2" flap along the opposite edge.



Fold tabs under.

Attach flaps to page base with tabs, 1/8" in from page edge

© 2015 Laura Denison



Card Flap Page

Cut a 5 1/2" x 8 1/2" section.

Score and fold at 4" from one edge and 1/2" from opposite edge.

Cut a 3/4" x 7 3/4" strip of accent cardstock.

Attach folded card flap with accent strip along edge of age.



© 2015 Laura Denison



Page 1



Page 2/3 and Page 8/9

© 2015 Laura Denison



Page 4/5



Page 6/7

Page 15

© 2015 Laura Denison



Page 10/11



Page 12

Page 16

© 2015 Laura Denison



Add pockets, envelopes, tags, and mattes to pages as desired. Embellish pages and cover as desired.

Congratulations your

Treasured Memories

© 2015 Laura Denison

is complete!

just add photos and memorabilia!